

4.21. Pickfaces and Replenishments setup

In a large, busy warehouse it is sometimes useful to designate some shelf locations as pickfaces. These locations are easily accessible for pickers, usually at floor level or the next level up in the racking. These pickfaces are then replenished from other, harder to reach locations somewhere in the warehouse.

Typically, these replenishments take place at a time when the activity does not get in the way of the busy pickers; at the beginning of the day or lunch time. A forklift driver will fetch the stock from the bulk location and place it in or near the pickface so that others can place it or open the cartons ready for picking.

Deciding which locations to replenish when can be hard to keep track of so mSupply has functionality to help and this is what is described here. There is quite a lot of setup involved so that's detailed on this page. The next page ([4.23. Pickfaces and Replenishments](#)) describes the actual functionality and how you use it.

Create pickface and bulk locations

The first thing you need to do is tell mSupply which locations can be used as pickfaces and which are used to store the bulk stock to replenish them with.

If the location doesn't exist in your system create it, if it does then open it for editing (see [4.06. Stock locations and location types](#) for details). You will see this window:



The screenshot shows the 'Edit location' window. The 'Code' field is 'A22A' and the 'Description' is 'Aisle A, position 22, level A'. There are three tabs: 'General', 'Layout', and 'Stock'. The 'General' tab is active. The 'Location type' is 'None'. The 'Replenishment location type' is 'None' and is highlighted with a red box. The 'Parent' is 'None'. There is a 'Summary' checkbox and a 'Comment' text area. The 'Total Volume' is '1.8 m3', 'Volume used' is '0 m3', 'Priority' is '0', and there is a 'Hold' checkbox. At the bottom are buttons for 'Delete', 'Cancel', 'OK', and 'OK & Next'.

Click on the Replenishment location type drop down list and select the type this location will be:

- **None:** The default for all locations and means that the location won't be selectable as a pickface and won't take part in replenishments.
- **Pickface:** means that this location can be selected as a pickface for an item and will be replenished.
- **Bulk:** means this location stores bulk stock that can be used to replenish pickfaces. Note that mSupply will **only** use stock in locations with a replenishment type of *Bulk* to replenish other locations. Any other stock in locations not set as *Bulk* type will be ignored in the automatic replenishment process. This means it is possible to protect stock that should not take part in the replenishment process by making sure its location has a replenishment type of *None*.

When you have finished assigning the replenishment type click on the **OK** or **OK & Next** button to save the changes. Repeat this process for all the locations that will be used as pickfaces or that will hold bulk stock that can be used to replenish the pickfaces.

Assign pickfaces to items

The next step is to assign pickfaces to items. To do this, find the item you want to set a pickface for and open its details window (see [4.01. About items](#) for details). Then click on the storage tab:

The screenshot shows the 'Item details' window for 'Amoxycillin 500mg Tablets'. The 'Storage' tab is selected in the left sidebar. The 'Default' section shows 'Default shelf location' set to 'None', 'Preferred pack size' as 1000, 'Outer pack size' as 24000, 'Volume per pack' as 0 m3, 'Outer pack volume' as 0 m3, and 'Weight per pack' as 1 kg. The 'Restricted to' dropdown is set to 'None'. The 'Pickface' section shows 'Pickface location' as 'A22A', 'Pickface pack size' as 1000, 'Trigger replenishment at' as 24 packs of 1000 Tablets, and 'Replenish up to' as 288 packs of 1000 Tablets. The 'Bulk' section shows 'Bulk shelf location' as 'a3', 'Trigger replenishment at' as 2 packs of 24000 Tablets, and 'Replenish up to' as 12 packs of 24000 Tablets. At the bottom are buttons for 'Delete', 'OK & Previous', 'OK & Next', 'Cancel', and 'OK'.

In the *Pickface* section set these fields:

- **Pickface location:** The location that will be used as a pickface for this item. This location will then be replenished with stock in Bulk type locations when replenishments are automatically generated by mSupply.
- **Pickface pack size:** The pack size that will be used in this location. mSupply uses this to determine how many bulk packs should be moved into the location and whether a repack needs

to be automatically carried out at the same time.

- **Trigger replenishments at:** If there are this number of packs (of *Pickface pack size*) or less in the pickface a replenishment will be generated for it when the “generate replenishments” function is run.
- **Replenish up to:** This is the maximum number of packs (of *Pickface pack size*) that fit in the location. mSupply will try to put enough stock into the location to bring it up to this number of packs. It will never put more than this number of packs in the location.

In the *Bulk* section set these fields:

- **Bulk shelf location:** The preferred bulk location for this item. If set, this is the first location that mSupply will try to take stock from to replenish this item's pickface (defined in the *Pickface* section described above). When running the automatic replenishment process, mSupply will work out the replenishment of the pickface first and then the replenishment for the preferred bulk location.
 - The pack size used in this preferred bulk location is the *Outer pack size* entered in the *Default* section.
 - Setting a preferred bulk location turns it into a two stage replenishment process; first, bulk stock is moved from the preferred bulk location into the pickface and second, stock is moved into the preferred bulk location from bulk stock. There might be a repack involved with the pickface replenishment but there will never be a repack with the preferred bulk location replenishment.
 - If you don't want this two-stage replenishment process simply leave the preferred bulk location empty.
- **Trigger replenishment at:** If there are this number of packs (of *Outer pack size*) or less in the bulk location a replenishment will be generated for it when the “generate replenishments” function is run.
- **Replenish up to:** This is the maximum number of packs (of *Outer pack size*) that fit in the location. mSupply will try to put enough stock into the location to bring it up to this number of packs. It will never put more than this number of packs in the location.

Define the users who can action replenishments

The final setup step is to tell mSupply which users can action replenishments. These are the users you can assign replenishments to.

Open a user for editing (see [25.15. Managing users](#) for details) and go to the *Permissions (3)* tab on the user's details window:

The screenshot shows the 'Edit user' dialog box for user 'sussol'. The 'Permissions (3)' tab is selected. The 'Can action replenishments' checkbox is checked and highlighted with a red box. Other permissions are also checked, including 'Virtual Stores', 'Reminders', 'Admin', 'Assets', 'Vaccines', 'Customer budgets', 'Registration', 'Requisitions', and 'Supplier Hub'.

Check the *Can action replenishments* checkbox and click on the OK button to save the changes.

Repeat this for every user who can be assigned to action replenishments.

This now completes the setup and you're ready to use the functionality. See the [4.23. Pickfaces and Replenishments](#) page for details on that.

Previous: [4.21. Forecasting](#) | | Next: [4.23. Pickfaces and Replenishments](#)

From:

<https://docs.msupply.org.nz/> - mSupply documentation wiki

Permanent link:

https://docs.msupply.org.nz/items:replenishments_setup?rev=1604415499

Last update: **2020/11/03 14:58**

