

4.01.02. Items - Storage tab

[Back to Item Details window](#)

The screenshot shows the 'Item details' window with the 'Storage' tab selected. The 'Item name' is 'Adrenaline (EPINEPHRINE), 1mg/1ml vial' and the 'Item code' is 'adr11v'. The 'Store' is set to 'General'. The 'Default' section includes fields for 'Default shelf location' (empty), 'Preferred pack size' (1000), 'Outer pack size' (24000), 'Volume per pack' (0 m3), 'Outer pack volume' (0 m3), and 'Weight per pack' (1 kg). The 'Restricted to' dropdown is set to 'None'. The 'Pickface' section includes 'Pickface location' (A22A), 'Pickface pack size' (1000), 'Trigger replenishment at' (24 packs of 1000 Tab), and 'Replenish up to' (288 packs of 1000 Tab). The 'Bulk' section includes 'Bulk shelf location' (A3A), 'Trigger replenishment at' (2 packs of 24000 Tab), and 'Replenish up to' (12 packs of 24000 Tab). At the bottom are buttons for 'Delete', 'OK & Previous', 'OK & Next', 'Cancel', and 'OK'.

Default section

Default shelf Location

The default shelf location for this item *in this store*. When you receive items into stock, they will be given the shelf location you enter here by default. You can always override it if you wish. Enter the first few characters of the location's code, then press the *Tab* key and select the location from the list displayed. If only one location code matches your entry it will be filled in automatically without having to select it from a list.

Preferred pack size

The Preferred pack size is the *default* pack size that will be assigned to incoming stock as it is received or when entering a purchase order. It will also be used in comparisons of quotations from suppliers to make sure the comparisons are for the same numbers of units.

Outer pack size

The Outer pack size is the number of *preferred pack size* packs in a carton (outer pack). **Not** the

number of units in a carton.

Volume per pack

The Volume per pack is the default volume per *preferred pack size* pack. This is the volume that will be used by default when receiving goods. We recommend you divide a carton volume by the number of *preferred pack size* packs in a carton to get this figure. mSupply always stores volumes in m3 (cubic metres), but you can enter a volume as millilitres (ml) or litres (l) by entering the appropriate abbreviation after the number representing the volume. e.g. enter “0.5l” to enter a volume of 0.5 litres (= 0.0005m3).

Here are some examples:

You enter	Value displayed	mSupply stores
30ml	30ml	0.00003 m3
1500L	1.5 m3	1.5 m3
600 L	600l	0.6 m3
1500 ml	1.5l	0.0015 m3

Outer pack volume

The Outer pack volume is the default volume of an *Outer pack size* pack of this item.

Weight per pack

The Outer pack volume is the gross weight of a *preferred pack size* pack in kg.

Restricted to

The **Restricted to** is the location type that this item must be restricted to. You can from a list of all active Location types. When something is selected here, all stock of this item that is received must be put in a location which is of the same location type. For example, all cool store locations could have been given a type of “cool” and then if the item you are editing should be kept in a cool store, choose that type here, and you will only be able to receive that item into a cool store location.

Pickface section

Used in the pickface replenishment functionality. See the [4.23. Pickfaces and Replenishments](#) page for details.

Pickface location

The Pickface location is the location that will be used as a pickface for this item. This location will then

be replenished with stock in Bulk type locations when replenishments are automatically generated by mSupply.

Pickface pack size

The Pickface pack size is the pack size that will be used in the Pickface location. mSupply uses this to determine how many bulk packs should be moved into the location and whether a repack needs to be automatically carried out at the same time.

Trigger replenishments at

If there are this number of packs (of *Pickface pack size*) or less in the *Pickface location*, a replenishment will be generated for it when the “generate replenishments” function is run.

Replenish up to

This is the maximum number of packs (of *Pickface pack size*) that fit in the *Pickface location*. mSupply will try to put enough stock into the *Pickface location* to bring it up to this number of packs. It will never put more than this number of packs in the *Pickface location*.

Bulk section

Again, this is used in the pickface replenishment functionality. See the [4.23. Pickfaces and Replenishments](#) page for details.

- **Bulk shelf location:** The preferred bulk location for this item. If set, this is the first location that mSupply will try to take stock from to replenish this item's pickface (defined in the *Pickface* section described above). When running the automatic replenishment process, mSupply will work out the replenishment of the pickface first and then the replenishment for the preferred bulk location.
 - The pack size used in this preferred bulk location is the *Outer pack size* entered in the *Default* section.
 - Setting a preferred bulk location turns it into a two stage replenishment process; first, bulk stock is moved from the preferred bulk location into the pickface and second, stock is moved into the preferred bulk location from bulk stock. There might be a repack involved with the pickface replenishment but there will never be a repack with the preferred bulk location replenishment.
 - If you don't want this two-stage replenishment process simply leave the preferred bulk location empty.
- **Trigger replenishment at:** If there are this number of packs (of *Outer pack size*) or less in the bulk location a replenishment will be generated for it when the “generate replenishments” function is run.
- **Replenish up to:** This is the maximum number of packs (of *Outer pack size*) that fit in the location. mSupply will try to put enough stock into the location to bring it up to this number of packs. It will never put more than this number of packs in the location.

Previous: [4.01.01. Items - General tab](#) | | Next: [4.01.03. Items - Misc\(ellaneous\) tab](#)

From:

<https://docs.msupply.org.nz/> - mSupply documentation wiki

Permanent link:

https://docs.msupply.org.nz/items:item_basics:tab_storage?rev=1678147660

Last update: **2023/03/07 00:07**

